
# **Local save camera images**


#### **Local save camera images**

- 1. Experimental preparation
- 2. How to run
- 3. Expected results

## 1. Experimental preparation

This example vio\_capture implements the MIPI camera image acquisition and local storage of images in two formats: RAW and YUV. The example flow chart is as follows:





- When the development board is powered off, connect the MIPI camera to the development board (with the blue side facing the HDMI interface).
- Connect the development board and the monitor via an HDMI cable
- Power on the development board and log in to the system

### 2. How to run

The sample code is provided in source code form and needs to be compiled and run using the make command. The steps are as follows:

```
sunrise@ubuntu:~$ cd /app/cdev_demo/vio_capture/
sunrise@ubuntu:/app/cdev_demo/vio_capture$ sudo make
sunrise@ubuntu:/app/cdev_demo/vio_capture$ sudo ./capture -b 16 -c 10 -h 1080 -w
1920
```

#### Parameter description:

- -b: RAW image bit number, IMX219 / IMX477 / OV5647 are all set to 16, only a few camera sensors need to be set to 8
- -c: Number of images to be saved
- -w: Width of saved images
- -h: Height of saved images

## 3. Expected results

After the program runs correctly, when the terminal stops printing, enter 0 or 1, then press Enter to start a random camera. The current directory saves the specified number of image files.

The RAW format is named in the raw\_\*.raw format, and the YUV format is named in the YUV\_\*.yuV format. The running log is as follows:

```
sunrise@ubuntu:/app/cdev_demo/vio_capture$ sudo ./capture -b 16 -c 10 -h 1080 -w
[INFO] board_id is 301, not need skip sci1.
Searching camera sensor on device: /proc/device-tree/soc/cam/vcon@0 i2c bus: 6
mipi rx phy: 0
INFO: Found sensor name:ov5647 on mipi rx csi 0, i2c addr 0x36,
config_file:linear_1920x1080_raw10_30fps_2lane.c
2000/01/01 08:18:54.877 !INFO [CamInitParam][0139]Setting VSE channel-0:
input_width:1920, input_height:1080, dst_w:1920, dst_h:1080
2000/01/01 08:18:54.877 !INFO [CamInitParam][0139]Setting VSE channel-1:
input_width:1920, input_height:1080, dst_w:1920, dst_h:1080
... omission ...
capture time :0
temp_ptr.data_size[0]:4147200
capture time :1
temp_ptr.data_size[0]:4147200
capture time :2
temp_ptr.data_size[0]:4147200
... omission ...
capture time :8
temp_ptr.data_size[0]:4147200
```

capture time :9

temp\_ptr.data\_size[0]:4147200

ov5647 sensor stop